

Re: How to set up in order to map to Window server from G5 computer

Re: How to set up in order to map to Window server from G5 computer

Source:

<http://www.tech-archive.net/Archive/Mac/microsoft.public.macintosh.general/2006-10/msg00019.html>

- *From:* Jon Hokama <jon@xxxxxxxxxxxxxxxxxxxx>
 - *Date:* Thu, 12 Oct 2006 05:51:32 +0000 (UTC)
-

Hello Helen,
Your welcome. Glad I could be of help.

–Jon–
Jon Hokama
Roland Schorr & Tower
<http://www.rolandschorr.com>

Hi Jon,

Thank you so much for your help. I was able to map after applying your instructions. You're a pro!

Cheers,
Helen
"Jon Hokama" <jon@xxxxxxxxxxxxxxxxxxxx> wrote in message
news:c386c21bc6b08c8bb677bc32c6e@xxxxxxxxxxxxxxxxxxxxxxxxxxxx

Hello Helen,
Sorry I was running around taking care of business. First thing is we want to make sure file services for Macintosh is loaded. You find it in Add/Remove Programs, Add/Remove Windows Components, Other Network Services, File Services for Macintosh. Check the box for File sharing.
Then go to Computer Management, Shared Folders, Shares. Right click on shares, from the pop up menu select New File Share, then create your share. Make sure to check the Apple Macintosh check box. On the Mac you may want to enable Apple Talk. Try it without first though. To enable Apple Talk go to the Apple Menu (top left hand corner of the screen), System Preferences, Network, Apple Talk tab, enable Apple Talk.
Hopefully

Re: How to set up in order to map to Window server from G5 computer

this will take care of your problem.

–Jon–

Jon Hokama

Roland Schorr & Tower

<http://www.rolandschorr.com>

Hi Jon,

I have try to log into the Windows server, gone into
Computer
Management console, right click on the Creative share but I
dont see
ANYTHING. Please advise me...I am really getting a bad
start on
this and I need to get this set up properly ASAP.

Thank you,

Helen

"Jon Hokama" <jon@xxxxxxxxxxxxxxxxxxxx> wrote in message
news:c386c21bc4a48c8bb3ca90b15a4@xxxxxxxxxxxxxxxxxxxxxxxxxxxx

Hello Helen,
Do you have File Services for Macintosh
enabled on the Windows
Server?
–Jon–
Jon Hokama
Roland Schorr & Tower
<http://www.rolandschorr.com>

Hi,

I am pretty much new to the
Mac world when it comes to
networking
it with Windows servers. I
am a network admin for a
small firm
and have no problem
mapping betw PCs and
Windows server. I
thought I have done the
right thing by installing the
Apple
protocol on the Windows
2000 and Windows 2003
(SBS) servers and
then enable sharing on the

Re: How to set up in order to map to Window server from G5 computer

folder I am trying to share. I have added the appropriate right for the Mac user to gain access to the share as well from the Permission tab of the folder.

When I try to map from the Mac G5 to the Windows 2000 server for example:
smb://192.168.200.101/creatives

It would prompt me to enter in the username and password and so I supply it and then I only get next the box that comes up which allows me to connect to MS UAM volume only. How do I get the Creatives share to show up so that I can not to that instead?

Would you be able to give me specific instructions to configure the server / G5 so that I can map to the share drive from the Mac computer.

Thank you,

Helen