

## Re: Cannot load the Hive

---

*Source:*

<http://www.tech-archive.net/Archive/Win2000/microsoft.public.win2000.general/2005-11/msg00169.html>

---

- *From:* "DL" <dl@xxxxxxxxxxxxxxxxxx>
  - *Date:* Sat, 5 Nov 2005 19:16:23 -0000
- 

Done the clean install, still gives hive errs, and others eg  
Stop inaccessible boot device,  
winnt\system32\config\systemcmd missing or corrupt  
Used a single good hd, no raid.

"Dave Patrick" <DSPatrick@xxxxxxxxxxxxxxxxxx> wrote in message  
[news:%23gGZNgj4FHA.632@xxxxxxxxxxxxxxxxxxxxxxxxxxxx](mailto:news:%23gGZNgj4FHA.632@xxxxxxxxxxxxxxxxxxxxxxxxxxxx)

> Might be time for that clean install.

>

> You'll want to boot the Windows 2000 setup disks or CD-Rom. The set of  
> four install disks can be created from your Windows 2000 CD-Rom; change to  
> the \bootdisk directory on the CD-Rom and execute makeboot.exe (from dos)  
> or makebt32.exe (from 32 bit) and follow the prompts.

>

> Then \*F6\* very early and very important (at setup is inspecting your  
> system) in the setup to prevent drive controller detection, and select S  
> to specify additional drivers. Then later you'll be prompted to insert the  
> manufacturer supplied Windows 2000 driver for your raid controller in  
> drive "A"

>

> If you wait and then S to specify additional drivers, then it may be too  
> late as Windows 2000 Setup at this point may have already assigned the  
> resources your drive's controller is wanting to use.

>

> When you get to the point, delete the existing NTFS and or other  
> partitions found. After you delete the partition(s) abort the install,  
> then again restart the pc booting the CD-Rom or setup disks to avoid  
> unexpected drive letter assignments with your new install.

>

> Be sure to apply these to your new install before connecting to any  
> network.

>

>

[http://download.microsoft.com/download/E/6/A/E6A04295-D2A8-40D0-A0C5-241BFECDD095E/W2KSP4\\_EN.EX](http://download.microsoft.com/download/E/6/A/E6A04295-D2A8-40D0-A0C5-241BFECDD095E/W2KSP4_EN.EX)

> <http://www.microsoft.com/technet/security/bulletin/MS03-043.msp>

> <http://www.microsoft.com/technet/security/bulletin/MS03-049.msp>

>

Re: Cannot load the Hive

> --  
>  
> Regards,  
>  
> Dave Patrick ....Please no email replies – reply in newsgroup.  
> Microsoft Certified Professional  
> Microsoft MVP [Windows]  
> <http://www.microsoft.com/protect>  
>  
> "DL" wrote:  
>> Background:  
>> Using Sil mirror raid, started getting intermittent event errors on Sil  
>> controller eg 'did not start'  
>> Certain apps exhibited odd behaviour.  
>> Broke the mirror, rebooted extreamly! slow boot.  
>> Rebooted a number of times with differing err msgs.  
>>  
>> Used last good config, ERD, Erdnt and recovery consul to restore backup  
>> and default hives, all to no effect.  
>> Tried a win reinstall on one hd, still get hive err.msgs.  
>>  
>> Run hd manu checking utility over both disks for a number of loops, all  
>> ok  
>> Run chkdsk all ok.  
>>  
>> At this stage I'm tending towards mobo problem.  
>> What think you?  
>> TY  
>  
>

---

• **Follow-Ups:**

- ◆ **Re: Cannot load the Hive**  
◇ From: Dave Patrick

• **References:**

- ◆ **Cannot load the Hive**  
◇ From: DL
- ◆ **Re: Cannot load the Hive**  
◇ From: Dave Patrick
- ◆ **Re: Cannot load the Hive**  
◇ From: DL
- ◆ **Re: Cannot load the Hive**  
◇ From: Dave Patrick

- Prev by Date: **Re: Win2000 acting strange**

Re: Cannot load the Hive

- Next by Date: ***Re: Cannot load the Hive***
- Previous by thread: ***Re: Cannot load the Hive***
- Next by thread: ***Re: Cannot load the Hive***
- Index(es):
  - ◆ ***Date***
  - ◆ ***Thread***