

## Re: can not access client resources

**Source:**

[http://www.tech-archive.net/Archive/Win2000/microsoft.public.win2000.ras\\_routing/2004-12/0022.html](http://www.tech-archive.net/Archive/Win2000/microsoft.public.win2000.ras_routing/2004-12/0022.html)

---

**From:** Bill Grant (*not.available\_at\_online*)

**Date:** 12/03/04

Date: Fri, 3 Dec 2004 16:09:15 +1100

What is the IP addressing scheme used on the remote LAN? From your posting, it looks as if both sites are using the same IP subnet. If that is the case, nothing will ever go over the VPN link. An IP address in the same IP subnet is assumed to be local. Traffic will go to the LAN NIC, not to a router or VPN link.

"Joe Bucar" <jbucar@hotmail.com> wrote in message  
news:%23VfNnmL2EHA.1152@TK2MSFTNGP14.phx.gbl...

> Hello,  
> I set up a VPN and the connection appears to be working. I just do not  
> understand why I can not see or access the resources on the company2.local  
> machine. When I do an explore it appears that it is going over the VPN to  
> the company2.local machine but when explore comes back I do not see mapped  
> drives on company2.local. My machine is a WinXP SP2 on a SBS 2003  
> network. The other server is a SBS 2003 system with 1 NIC card. The  
> following is a ipconfig on my PC after the VPN connection. I can ping the  
> other server.  
>  
> Windows IP Configuration  
>  
>  
> Ethernet adapter Local Area Connection:  
>  
> Connection-specific DNS Suffix . : company1.local  
> IP Address. . . . . : 192.168.16.167  
> Subnet Mask . . . . . : 255.255.255.0  
> Default Gateway . . . . . : 192.168.16.2  
>  
> PPP adapter Connect to Small Business Server:  
>  
> Connection-specific DNS Suffix . : company2.local  
> IP Address. . . . . : 192.168.16.13  
> Subnet Mask . . . . . : 255.255.255.255  
> Default Gateway . . . . . : 192.168.16.13  
>  
> Thank You,

microsoft.public.win2000.ras\_routing: Re: can not access client resources

> *Joe*

>