

# Re: can't access ICS on client

---

*Source:*

[http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.network\\_web/2005-07/msg00031.html](http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.network_web/2005-07/msg00031.html)

---

- *From:* "Mirko DZuovic" <[dzuovic@xxxxx](mailto:dzuovic@xxxxx)>
  - *Date:* Fri, 1 Jul 2005 07:33:39 +0200
- 

thank you steve, but ...

can you tell me somethig more lookin in my seting for client and for host,

## Windows IP Configuration

Host Name . . . . . : Mirko  
Primary Dns Suffix . . . . . :  
Node Type . . . . . : Unknown  
IP Routing Enabled. . . . . : Yes  
WINS Proxy Enabled. . . . . : No

## Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix . :  
Description . . . . . : Realtek RTL8139 Family PCI Fast  
Ethernet NIC  
Physical Address. . . . . : 00-01-2E-02-02-BF  
Dhcp Enabled. . . . . : No  
IP Address. . . . . : 192.168.0.1  
Subnet Mask . . . . . : 255.255.255.0  
Default Gateway . . . . . :

## PPP adapter Internet ISDL:

Connection-specific DNS Suffix . :  
Description . . . . . : WAN (PPP/SLIP) Interface  
Physical Address. . . . . : 00-53-45-00-00-00  
Dhcp Enabled. . . . . : No  
IP Address. . . . . : 195.66.175.111  
Subnet Mask . . . . . : 255.255.255.255  
Default Gateway . . . . . : 195.66.175.111  
DNS Servers . . . . . : 195.66.160.1  
195.66.160.2  
NetBIOS over Tcpip. . . . . : Disabled

## Windows IP Configuration

Re: can't access ICS on client

Host Name . . . . . : imeohn  
Primary Dns Suffix . . . . . :  
Node Type . . . . . : Unknown  
IP Routing Enabled. . . . . : No  
WINS Proxy Enabled. . . . . : No  
Ethernet adapter Local Area Connection:  
  
Connection-specific DNS Suffix . :  
Description . . . . . : Intel(R) PRO/100 VM Network  
Connection  
Physical Address. . . . . : 00-02-A5-26-02-7F  
Dhcp Enabled. . . . . : No  
IP Address. . . . . : 192.168.0.5  
Subnet Mask . . . . . : 255.255.255.0  
Default Gateway . . . . . : 192.168.0.1  
DNS Servers . . . . . : 192.168.0.1

--  
Pozdrav, Mirko.

"Steve Winograd [MVP]" <winograd@xxxxxxxx> wrote in message  
[news:qiu7c1p66ripet3nma47bnip20jk31vk5j@xxxxxxxx](mailto:news:qiu7c1p66ripet3nma47bnip20jk31vk5j@xxxxxxxx)  
> In article <O4bj#RWfFHA.4008@xxxxxxxxxxxxxxxxxxxx>, "Mirko D@uovic"  
> <dzuovic@xxxx> wrote:  
>> I have recently try to set up ICS to share a dialup internet connection.  
>> Can't access internet from a clients using IE. Can't ping any web address  
>> from a clients. But, when ping web address from a host and then ping  
>> that  
>> same web address from a client everything is fine. No errors. Fakt is, I  
>> can access any web address from a client but first must access that web  
>> address from a host. ??  
>>  
>>  
>> Thanks, Mirko.  
>  
> The host's DNS relay agent might not be working properly. Try  
> manually assigning TCP/IP properties to the client:  
>  
> IP Address: 192.168.0.x (1<x<255)  
> Subnet Mask: 255.255.255.0  
> Default Gateway: 192.168.0.1  
> DNS Server = your ISP's DNS server  
>  
> You can find your ISP's DNS server address by connecting to the  
> Internet and then entering the "ipconfig /all" command in a command  
> prompt window.  
>  
> If that doesn't fix the problem, try disabling ICS on the host and  
> then re-enabling ICS.

Re: can't access ICS on client

Re: can't access ICS on client

> --  
> Best Wishes,  
> Steve Winograd, MS-MVP (Windows Networking)  
>  
> Please post any reply as a follow-up message in the news group  
> for everyone to see. I'm sorry, but I don't answer questions  
> addressed directly to me in E-mail or news groups.  
>  
> Microsoft Most Valuable Professional Program  
> <http://mvp.support.microsoft.com>

---

• *Follow-Ups:*

◆ ***Re: can't access ICS on client***

◇ *From:* Steve Winograd [MVP]

- Prev by Date: ***Re: Hide PC in Peer to Peer WORKGROUP***
- Next by Date: ***Re: Hide PC in Peer to Peer WORKGROUP***
- Previous by thread: ***Hide PC in Peer to Peer WORKGROUP***
- Next by thread: ***Re: can't access ICS on client***
- Index(es):
  - ◆ ***Date***
  - ◆ ***Thread***