

## Re: What parameter VS.Net passes to "netcf.all.wce4.armv4.cab" file to

---

*Source:*

<http://www.tech-archive.net/Archive/PocketPC/microsoft.public.pocketpc.developer/2005-09/msg00113.html>

---

- *From:* "Peter Foot [MVP]" <[feedback@xxxxxxxxxxxxxxxxxxxxxxxx](mailto:feedback@xxxxxxxxxxxxxxxxxxxxxxxx)>
  - *Date:* Sat, 3 Sep 2005 15:19:09 +0100
- 

you should launch wceoad.exe with the argument /noaskdest /noui followed by the path to your cab file. The install will then be virtually silent (will display in title bar only)

Peter

—

Peter Foot  
Windows Embedded MVP  
<http://www.inthehand.com> | <http://www.peterfoot.net>

"Arif" <[Arif@xxxxxxxxxxxxxxxxxxxxxxxx](mailto:Arif@xxxxxxxxxxxxxxxxxxxxxxxx)> wrote in message [news:2BEF8CBA-664C-4152-8AD3-32656DBF622D@xxxxxxxxxxxxxxxxxxxx](mailto:news:2BEF8CBA-664C-4152-8AD3-32656DBF622D@xxxxxxxxxxxxxxxxxxxx)  
> When I manually execute "netcf.all.wce4.armv4.cab" file on WinCE.Net  
> device,  
> it asks for location to install. But when VS.Net deploys and executes this  
> file there is no dialog box to ask for location to install. What parameter  
> VS.Net passes to this .cab file to prevent install location option.  
>  
> I want to install this "netcf.all.wce4.armv4.cab" file on warm boot but it  
> should not ask for install location.  
> Please help.  
>  
> Arif.

---

- *Follow-Ups:*
  - ◆ [Re: What parameter VS.Net passes to "netcf.all.wce4.armv4.cab" file to](#)  
◇ *From:* Arif
- *References:*
  - ◆ [What parameter VS.Net passes to netcf.all.wce4.armv4.cab file to](#)

Re: What parameter VS.Net passes to "netcf.all.wce4.armv4.cab" file to

◇ *From:* Arif

- Prev by Date: [Problem turning on nic USING OID DOT11 NIC POWER STATE](#)
- Next by Date: [VS 2005 Serial Port read?](#)
- Previous by thread: [What parameter VS.Net passes to netcf.all.wce4.armv4.cab file to](#)
- Next by thread: [Re: What parameter VS.Net passes to "netcf.all.wce4.armv4.cab" fil](#)
- Index(es):
  - ◆ [Date](#)
  - ◆ [Thread](#)