

## Re: MS-DOS Eiting

**Source:**

<http://www.tech-archive.net/Archive/Win2000/microsoft.public.win2000.general/2004-10/2752.html>

---

**From:** Eric McG (*dontbother\_at\_att.net*)

**Date:** 10/22/04

Date: Thu, 21 Oct 2004 20:00:44 -0400

If you have an AV app scanning your system during startup, try disabling this feature temporarily.

If no joy, see if changing the file's attribute to read-only helps.

--

Hope this helps..Reply in newsgroup only.

Eric McGillicudy

"Alex Vinokur" <alexvn@big-foot.com> wrote in message  
news:2tq0evF214i7aU1@uni-berlin.de...

>

> "Eric McG" <dontbother@att.net> wrote in message  
news:eNwkMH1tEHA.3460@TK2MSFTNGP15.phx.gbl...

> > You're welcome...and thanks for the feedback!

> >

> > ---

> > Eric

> >

> > "Alex Vinokur" <alexvn@big-foot.com> wrote in message  
> > news:2tp7eaf22i259U1@uni-berlin.de...

> > >

> > > "Eric McG" <dontbother@att.net> wrote in message  
> > > news:Ox7ZyTHtEHA.992@TK2MSFTNGP10.phx.gbl...

> > > > I've read that this is sometimes caused by a virus deleting the  
autoexec.nt

> > file

> > > in %SystemRoot%\System32 folder.

> > >

> > > > Do a search for the autoexec.nt file.

> > > >

> > > > You should have another copy in %SystemRoot%\Repair folder. If so, copy  
it

> > to

> > > the %SystemRoot%\System32 folder.

> > > [snip]

> > >

> > > I had the same problem.

> > > And I fixed that owing to your advice.

> [snip]

>

> It turned out that the problem was resolved only partially.

> After restart/shut down the autoexec.nt file is missing in

%SystemRoot%\System32.

> So, I need to copy it manually from %SystemRoot%\Repair to  
%SystemRoot%\System32 after each restart/shut down.

microsoft.public.win2000.general: Re: MS-DOS Eiting

>  
> What could cause removing autoexec.nt from %SystemRoot%\System32?  
>  
> --  
> Alex Vinokur  
> email: alex DOT vinokur AT gmail DOT com  
> <http://mathforum.org/library/view/10978.html>  
> <http://sourceforge.net/users/alexvn>  
>  
>  
>