

Re: Ram Disk by arsoft didn't work.....

Source:

<http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.embedded/2005-01/0811.html>

From: KM (*konstmor_at_nospam_yahoo.com*)

Date: 01/19/05

Date: Wed, 19 Jan 2005 15:09:55 -0800

Andrea,

Last time I worked with MS DOS Network Client many, many years ago.. I don't recall all the details now.

GUI stuff (wizards, etc.) usually does not help you much with troubleshooting network problems.

About the command I was asking for what you do on the DOS client.

Do you use net use command? Why don't you want to type a password?

Also, set "ForceGuest" value of

[HKLM\SYSTEM\FBA\RegMigrate\HKLM\System\CurrentControlSet\Control\Lsa] key to "1". (at runtime or in

your Configuration under "File Sharing" component's registry section).

You may also want to post the question to a network newsgroup.

--

Regards,

KM, BSquare Corp.

>

>

> "KM" wrote:

>

> > Andrea,

> >

> > You would need to give us some more info about your problems if you want a help.

> >

> > By Dos client PC - do you mean MS DOS running on a PC?

>

> Yes, I have an application running on ms dos OS with network card NE2000

> compatible. I installed ms client and I ping with XPE pc. I use tcp/ip

> protocol and it work.

>

> > Do you see the same issue accessing a XP Pro machine (over NetBEUI?) from the same DOS client

>

> No, it works fine. Besides before yesterday it still worked fine on XPE!

>

> > How do you use the share? Show us the exact commands please.

>

> I hope to make myself understood: In the property of "My computer" I change

> name and workgroup (start wizard). Next in the folder options i enabled "Use

> simple sharing ...". Then I right click on my drive, I selected tab "sharing"

> and I click on "if you understood". Start a new wizard and it ask my

microsoft.public.windowsxp.embedded: Re: Ram Disk by arsoft didn't work.....

> type of network, if there's a internet connection, name of pc and workgroup
> etc..... Then in the "sharing" appeared two options: "Share this folder on
> the network" and "allow network users to change my files". I check togheter
> and then, before yersterday, it worked fine.
>
>
>
> >
> > KM
> >
> > > Thank you KM !! Yes I included FAT component in my image, but it didn't work.
> > > At least I finded another virtual ram disk in the net and it works. But now I
> > > have a problem with a shared drive. Dos client Pc saves some data in my XPe
> > > sharing drive. I have used net config wizard to configure my networks (no
> > > domain and static IP addresses), I enabled file sharing and all works fine,
> > > but from yesterday
> > > dos client never access to shared drives because it wants a password. I
> > > don't understand why. Exscuse for my bad english, Can you help me ?
> > >
> > >
> > > "KM" wrote:
> > >
> > >> Andrea,
> > >>
> > >> Make sure you've got FAT component in your image.
> > >>
> > >> KM
> > >>
> > >> > Hello, I'm newbie and i have a problem with the software in object. My XPe
> > >> > works on a compact flash and I need to create a virtual partition to share in
> > >> > a network. I would like to use arsoft's product, but when I install it, I can
> > >> > see it in the explorer windows but i can't access to it. How can I understand
> > >> > if I missing some essential files in my XPe image ???
> > >> >
> > >> > Thank you
> > >>
> > >>
> > >>
> >
> >
> >