

Re: Autoplay doesn't work.

Source:

http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.perform_maintain/2004-04/0445.html

From: Kaylene aka Taurarian (*taurarian_at_REMOVE_CAPS_hotmail.com*)

Date: 04/03/04

Date: Sat, 3 Apr 2004 16:37:42 +1000

Only one:

http://www.kellys-korner-xp.com/xp_tweaks.htm

Autoplay Repair Tool #234

"willytel" <wtelwak@comcast.net> wrote in message

news:12f3401c418d7\$53de2840\$a001280a@phx.gbl...

> Thanks. I have already seen these tips. That is were my

> reference to the hex 91 in my original message comes from.

> The tip says:

>

> ~Make sure that the AutoPlay feature is enabled in the

> registry:

> ~Click Start, and then click Run.

> ~Type regedit, and then click OK.

> ~In Registry Editor, locate the following registry key:

>

>

> ~HKEY_LOCAL_MACHINE\System\CurrentControlSet\Services\CDRom

>

> ~In the right pane, go to step g if the value for Autorun

> is 1.

> ~If the value for Autorun is 0, right-click Autorun, and

> then click Modify.

> ~In the Edit DWORD Value dialog box, type 1 under Value

> data, and then click OK.

> ~A value of 0xb5 in the following registry key turns off

> the AutoRun feature for CDs:

>

>

> ~HKEY_CURRENT_USER\SOFTWARE\Microsoft\Windows\CurrentVersio

> n\Policies\Explorer\NoDriveTypeAutoRun

>

>

>

> ~You must set the hexadecimal value to 91 to enable the

> AutoRun feature.

> ~On the File menu, click Exit.

>
>
> *The first step was set for "0" and I reset it to "1". But*
> *the value in the second set in my registry was "5f00 00*
> *00". I am not sure how to set it to "91" as stated above.*
> *When I hit Modify there was no hexadecimal value setting*
> *to change. So I'm not sure how to fix that.*
>
> *As for the the second article.... I am logged in as an*
> *Administrator.*
>
> *Any other tips?*
>
> *Thanks.*
>
> *Bill.*
>
> >-----Original Message-----
> >Here are two links that may or may not assist:
> ><http://support.microsoft.com/?id=330135>
> >*The AutoRun or AutoPlay Feature Does Not Work*
> >[http://support.microsoft.com/default.aspx?scid=kb;EN-](http://support.microsoft.com/default.aspx?scid=kb;EN-US;314855)
> >[US;314855](http://support.microsoft.com/default.aspx?scid=kb;EN-US;314855)
> >*CD-ROM May Not Run Automatically in Windows XP*
> >
> >"WillyTel" <anonymous@discussions.microsoft.com> wrote in
> >message
> >>news:175a401c4182a5c49db760a101280a@phx.gbl...
> >> *I had to do a System Restore the other day due to a*
> >> *problem of updating my sound card drivers. Everything*
> >> *appears to work well but now my CD and DVD drives do not*
> >> *autoplay when I insert a disk. I've checked the obvious*
> >> *and verified the options. Even followed the regedit tip*
> >> *(except the one that indicated to change a hex value to*
> >> *91*
> >> *because it didn't seem to follow correctly). My question*
> >> *is should I remove XP SP1 and re-install it? If I remove*
> >> *SP1 will I cause more problems? Thanks for any tips or*
> >> *responses. Bill.*
> >
> >
> >
> >