

Re: "Turn Off Computer" When Exiting From Screen Saver

Source:

http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.perform_maintain/2006-05/msg00226.htm

- *From:* "Wesley Vogel" <123WVogel955@xxxxxxxxxxxxx>
 - *Date:* Fri, 12 May 2006 20:39:49 -0600
-

Shouldn't you have asked some questions instead of presuming to know how I setup my computer?

You are correct.

The first thing that I should have asked was, "Do you have a four year old?"

Making Good Newsgroup Posts
<http://www.dts-l.org/goodpost.htm>

MAKE A GOOD NEWSGROUP POST
<http://home.satx.rr.com/badour/html/post.html>

Newsgroups – Unanswered Questions
<http://www.michna.com/kb/Newsgroups.htm>

How to ask a question
<http://support.microsoft.com/?id=555375>

—

Hope this helps. Let us know.

Wes
MS-MVP Windows Shell/User

In [news:w4CdnXIOVaBqt_jZnZ2dnUVZ_tKdnZ2d@xxxxxxxxxxxxx](mailto:w4CdnXIOVaBqt_jZnZ2dnUVZ_tKdnZ2d@xxxxxxxxxxxxx),
M and D <m_and_d@xxxxxxxxxxxxx> hunted and pecked:

Shouldn't you have asked some questions instead of presuming to know how I setup my computer?

The problem turned out to be a program installed in my 4-year old's account that was not closing properly, which in turn prevented his account from logging off properly. I had to uninstall and reinstall the program to fix the problem.

Re: "Turn Off Computer" When Exiting From Screen Saver

Good luck to you.

Steven

"Wesley Vogel" <123WVogel955@xxxxxxxxxxxx> wrote in message
news:eoAgfhhdGHA.3348@xxxxxxxxxxxxxxxxxxxxxxxxxxxx

To get rid of the screen saver password.

Right click the Desktop | Properties | Screen Saver tab |
UNSelect the On resume, password protect check box.
If Fast User Switching is turned on, UNSelect the On resume, display
Welcome screen check box. | Click Apply | Click OK

On resume

[[Specifies whether the logon window is displayed when you resume using
the computer after the screen saver has started running. If logging on
requires a password, you will have to type the password when you resume
work.]]

--

Hope this helps. Let us know.

Wes
MS-MVP Windows Shell/User

In news:lb-dnePJz5ldKf_ZnZ2dnUVZ_v6dnZ2d@xxxxxxxxxxxx,
M and D <m_and_d@xxxxxxxxxxxx> hunted and pecked:

I can exit out of my screen saver by moving my mouse. Most
of the time,
this brings me right back to the desktop without a problem.
But
sometimes, when I exit my screen saver, Windows XP will
display the
"Turn off computer" message and I have to click on the
Cancel button to
get rid of it. And sometimes the "Turn off computer"
message will
reappear, so I have to click on Cancel again. On occasion
I've had to
cancel the "Turn off computer" message several times before
I can
finally get back to work.

How can I fix this? Seems to me XP shouldn't display the
"Turn off
computer" message when I exit my screen saver. Thanks for
any help.

Steven

Re: "Turn Off Computer" When Exiting From Screen Saver