

Re: Kodak

Source:

<http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.photos/2006-09/msg00178.html>

- *From:* Georgew6 <Georgew6@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx>
 - *Date:* Sat, 23 Sep 2006 19:41:01 -0700
-

I just tried to post and think it was lost, but if this is a dupe. I am sorry. The instructions were excellent here as my problem was the same. Too bad Kodak does not have the confidence in its product to give us a choice as to whether or not we want to make easyshare the default vierer. If they do, it is hidden some place.

My files are still all of the TYPE EASYSHARE.JPG and that includes ones changed by EASYSHARE. On XP Professional is their a way to change them all back to simply JPG or whatever. I can change the name and extension, but the TYPE does not change when I bring up the files.

Now, I hope that I can remove EASYSHARE once and for all. It is not the worst program, but sending my pictures with ads to buy Kodak products should be my choice and Kodak will have to give me a cut if I choose to send them that way.

Well, any answer as to change the type will be appreciated. Thanks, George.

"John Inzer" wrote:

Jack Couse wrote:

When ever i down load or open pictures from my pictures they always open in Kodak, How do I stop Kodak from being the default and going back to me chosing how to open my pictures.

Thanks Jack

=====

Have a look at this article:

(307859) HOW TO: Change File Associations in Windows XP
<http://support.microsoft.com/?kbid=307859>

More info:

Re: Kodak

Try this...open an image folder and right click one of your image files...from the menu, select...Open With / Choose Program.

Make your choice from the list or Browse to the correct program if it is not in the list.

If you want the default...choose..."Windows Picture and Fax viewer"

Once you make your selection...be sure to check the box that says: "Always use the selected program to open this kind of file". (you will need to do this for each format...jpg, .tif, .gif...etc.)

Also...you can right click an image and choose Properties / Change Button...choose the program you wish to use and click...OK / Apply / OK.

Also...in WinXP, you can go to...My Computer / Tools / Folder Options / File Types tab...

And the following links may be useful:

Repair image file type associations in Windows XP
<http://windowsxp.mvps.org/imgassofix.htm>

Windows® XP File Association Fixes
http://www.dougknox.com/xp/file_assoc.htm

*****Notice*****

This is not tech support
.....I am a volunteer.....

Solutions that work for
me may not work for you.

Proceed at your own risk.

John Inzer
Picture It! MVP

Digital Image
Highlights and FAQs
<http://tinyurl.com/aczzp>

Need a Web Host?
*****Consider*****

Re: Kodak

Re: Kodak

Annex Technologies

<http://www.annex.com/>
