

Re: PC pointing to DC in other locations

Source:

http://www.tech-archive.net/Archive/Windows/microsoft.public.windows.server.active_directory/2006-08/msg00141

- *From:* Razvan Despa <RazvanDespa@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx>
 - *Date:* Wed, 26 Jul 2006 03:46:01 -0700
-

Hi,

Thanks for the fast answer.

I have checked the configuration the setup is exactly in the way that you recomand:

The site where i want my PC to connect is A and i added my subnet to this site;

The site where my PC is connecting is B and does not have any information about my subnet.

Very strange !!

Thanks,

—

Razvan Despa

IT assistent
Romania

"Frederik De Muyter" wrote:

You will need to add the subnets to your sites for the client.

An example will explain beter:

Client PC --> 10.10.10.1/24

add the subnet the client belongs to the site where you want the client to authenticate.

Go to sites and services --> choose subnets add subnet 10.10.10.0
255.255.255.0 to you subnet and assign the subnet to the right site.

Info:

<http://www.awprofessional.com/articles/article.asp?p=26866&rl=1>

Hope this is helpfull.

Re: PC pointing to DC in other locations

"Razvan Despa" schreef:

Hi,

I already have splitted te domain by sites (the domain is member in a forest – the sites are necessities for the replication).

Example:

- I have a PC1 in location A;
- I have 2 DC in location A (all roles for the domain are on these 2 DC – PDC emulator, GC, Master Role, etc.);
- location A – switch 100 Mbits, without network problems;

– I have 1 DC in location B (also a GC);

From time to time the PC1 is getting the authentications from DC in B;

It is something that can be setup in DNS for querry first the DC in the same location?

--

Razvan Despa

IT assistent
Romania

"JammyÃ¹ÀÙ'Ã" wrote:

You Need AD Site!

By Default pc client will logon to the same ad site DC.

"Razvan Despa"

<RazvanDespa@xxxxxxxxxxxxxxxxxxxxxxxxxxxx> wrote in
message

news:991C031D-EDEF-4454-AFA7-AC84DACA3D59@xxxxxxxxxxxxxxxxxxxx

Hi all,

We have a child domain with 15 DC
spreaded in several locations. From time
to time the PC are authenticating on DCs in
other locations, even if in
the
same location I have another 2 DC. All
actions after the authenticationa
are taking a lot of time when the user is
trying to access the file server

Re: PC pointing to DC in other locations

(queryng again to the DC for authentication).

Do you know a way to force the PCs to search in list of DC before authenticate?

It is a way to setup in DHCP the addresses of the local DC?

--

Razvan Despa

IT assistent
Romania