

Re: Credentials and net use problem after IPSec VPN is build

Source:

<http://www.tech-archive.net/Archive/Windows/microsoft.public.windows.server.networking/2008-10/msg00402.html>

- *From:* Juha <Juha@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx>
 - *Date:* Thu, 30 Oct 2008 22:48:00 -0700
-

Thanks

Yes they do logon to domain allways. It is funny that the other domain having this issue has also a win-radius server. When giving credentials to VPN FW they give domain credentials to FW. In the FW there aren't any user names or passwords it checks them from win-Radius server. But still they need to give them again when trying to open a share.

In radius scenario the RRAS is not enabled.

Rgs,

Juha

"Robert L. (MS-MVP)" wrote:

Are they logon domain (even they don't connect to domain the domain physically) using domain credentials? If you logon local computer using their local username. They may have this issue. Or this post may have more details.

Can't map network drives over VPN
<http://www.chicagotech.net/netforums/viewtopic.php?p=8355#8355>

—
Bob Lin, MS-MVP, MCSE & CNE
Networking, Internet, Routing, VPN Troubleshooting on
<http://www.ChicagoTech.net>
How to Setup Windows, Network, VPN & Remote Access on
<http://www.HowToNetworking.com>
"Juha" <Juha@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx> wrote in message
news:0F9B5348-BE5E-4624-9516-B5B326C51256@xxxxxxxxxxxxxxxxxxxxx

Hi

Re: Credentials and net use problem after IPsec VPN is build

I have this problem in two separate systems.

- 2003 R2 server domain
- VPN FireWall where IPsec VPN is terminated
- Third Party IPsec VPN Client SW where usernames and pws are same as in the server
- Net use /persistent:no

After the VPN tunnel is build I try to run "VPNLoginScript.bat" which maps the drives to shares. For some reason I get this output very often:

```
net use y: /d
y: was deleted successfully.
```

```
net use y: \\192.168.1.10\Share
The password is invalid for \\192.168.1.10\Share.
```

```
Enter the user name for '192.168.1.10': MyLoginName@DomainName
Enter the password for 192.168.1.10:
The command completed successfully. <---- I can now open the share but why it asks credentials?
```

If I place user name in the shorter way, I get this:

```
net use y: \\192.168.1.10\Share
The password is invalid for \\192.168.1.10\Share.
```

```
Enter the user name for '192.168.1.10': MyLoginName
```

```
To connect DomainName\MyLoginName to 192.168.1.10, press ENTER, or type a
```

```
new user name <---- This appears until i give the user name in syntax
```

```
MyLoginName@DomainName
```

This might be DNS problem but I wonder if there is a way to get rid of these credentials questions. After all, when I login to a "VPNLaptop" I do give domain credentials. Why they are asked again?

At least, is there a way to get a graphical Window asking for credentials?

Thanks,

Juha

P.S. The second place where I have this problem has a Radius Win Server

Re: Credentials and net use problem after IPsec VPN is build

and
the FW is a Radius Client for that. The behaviour is same.

I have tested scripts having some ping, static DNS server settings and
flushdns/registerdns commands but not really happy with them.