

Re: Changed NIC now can't see SBS in domain on local PCs

Source:

<http://www.tech-archive.net/Archive/Windows/microsoft.public.windows.server.sbs/2006-11/msg03338.html>

- *From:* picaw <picaw@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx>
 - *Date:* Sun, 19 Nov 2006 14:39:02 -0800
-

Hmmm – hard to see how "all works fine" then! How did you change your IPs?
Did you run the CEICW again? Use the change server IP wizard?
Try posting an unedited ipconfig /all from this server & from a workstation.

Pc :

```
F:\Documents and Settings\administrator.OGGLE>ipconfig /all
```

Windows IP Configuration

```
Host Name . . . . . : oggle2a
Primary Dns Suffix . . . . . : oggle.local
Node Type . . . . . : Hybrid
IP Routing Enabled. . . . . : No
WINS Proxy Enabled. . . . . : No
DNS Suffix Search List. . . . . : oggle.local
```

Ethernet adapter Local Area Connection 4:

```
Connection-specific DNS Suffix . :
Description . . . . . : Intel(R) PRO/1000 GT Desktop Adapter
Physical Address. . . . . : 00-0E-0C-BA-E5-8E
DHCP Enabled. . . . . : No
IP Address. . . . . : 192.168.21.200
Subnet Mask . . . . . : 255.255.255.0
Default Gateway . . . . . : 192.168.21.2
DNS Servers . . . . . : 192.168.21.2
158.152.1.43
```

SBS:

```
Microsoft Windows [Version 5.2.3790]
(C) Copyright 1985–2003 Microsoft Corp.
```

```
C:\Documents and Settings\Administrator>ipconfig /all
```

Re: Changed NIC now can't see SBS in domain on local PCs

Windows IP Configuration

Host Name : sbserver
Primary Dns Suffix : oggle.local
Node Type : Unknown
IP Routing Enabled. : Yes
WINS Proxy Enabled. : Yes
DNS Suffix Search List. : oggle.local

PPP adapter RAS Server (Dial In) Interface:

Connection-specific DNS Suffix . :
Description : WAN (PPP/SLIP) Interface
Physical Address. : 00-53-45-00-00-00
DHCP Enabled. : No
IP Address. : 169.254.15.36
Subnet Mask : 255.255.255.255
Default Gateway :
NetBIOS over Tcpip. : Disabled

Ethernet adapter LAN Connection:

Connection-specific DNS Suffix . :
Description : Intel(R) PRO/100 VE Network Connection
Physical Address. : 00-0C-F1-FD-4C-85
DHCP Enabled. : No
IP Address. : 172.16.1.2
Subnet Mask : 255.255.255.0
Default Gateway : 172.16.1.254
NetBIOS over Tcpip. : Disabled

Ethernet adapter New Server Local Area Connection:

Connection-specific DNS Suffix . :
Description : Intel(R) PRO/1000 GT Desktop Adapter
Physical Address. : 00-0E-0C-BA-D6-7A
DHCP Enabled. : No
IP Address. : 192.168.21.2
Subnet Mask : 255.255.255.0
Default Gateway :
DNS Servers : 192.168.21.2
NetBIOS over Tcpip. : Disabled

.

Re: Changed NIC now can't see SBS in domain on local PCs