

# Re: Local drives mapping

---

*Source:*

[http://www.tech-archive.net/Archive/Windows/microsoft.public.windows.terminal\\_services/2006-10/msg00637.html](http://www.tech-archive.net/Archive/Windows/microsoft.public.windows.terminal_services/2006-10/msg00637.html)

---

- *From:* "Vera Noest [MVP]" <[vera.noest@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx](mailto:vera.noest@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx)>
  - *Date:* Thu, 26 Oct 2006 12:59:19 -0700
- 

What exactly is the problem, then?  
Redirected drives are \*not\* assigned a drive letter, is that what you mean?  
In My Computer, your redirected local drives are shown as  
"C on <your\_client\_name>"  
"D on <your\_client\_name>" etc.

Do you see them in My Computer?

---

Vera Noest  
MCSE, CCEA, Microsoft MVP – Terminal Server  
TS troubleshooting: <http://ts.veranoest.net>  
\_\_\_ please respond in newsgroup, NOT by private email \_\_\_

=?Utf-8?B?bWF0M3k=?= <mat3y@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx> wrote on 26 okt 2006 in microsoft.public.windows.terminal\_services:

There are no new events in EventLog.  
This Server is in the OU SBSServer with no setting applied for terminal services.  
We are using RDP Client 5.1.2600.2180.

If I try \\tsclient there are all of the client drives.

"Vera Noest [MVP]" wrote:

Anything in the EventLog?  
Any GPOs?  
Which rdp client are you using?

---

Vera Noest  
MCSE, CCEA, Microsoft MVP – Terminal Server  
TS troubleshooting: <http://ts.veranoest.net>  
\*----- Please reply in newsgroup -----\*

=?Utf-8?B?bWF0M3k=?= <mat3y@xxxxxxxxxxxxxxxxxxxxxxxxxxxxxx> wrote

Re: Local drives mapping

on  
26 okt 2006:

Client Settings->Connection-> checked Use connection settings  
from user settings Disable Drive mapping is off.

"Vera Noest [MVP]" wrote:

Check if drive mapping is enabled on the  
Terminal Server, in  
Terminal Services Configuration – rdp-tcp  
properties

---

Vera Noest  
MCSE, CCEA, Microsoft MVP – Terminal  
Ser