

## Re: camera and scanner wizard

**Source:**

<http://www.tech-archive.net/Archive/WinXP/microsoft.public.windowsxp.photos/2004-03/0628.html>

---

**From:** Ron (RGaba\_at\_aol.com)

**Date:** 03/20/04

Date: Fri, 19 Mar 2004 17:00:02 -0800

Try what Yves recommends. I tried it today and it fixed my problem... YEAH!!!!

>-----Original Message-----

>No need to drag each picture. When the file names are displayed, hold the

>Ctrl key down and press the letter A. This selects (highlight in blue) all

>the files in the folder. Hold the Ctrl key down and press the letter C. This

>copies all the files to your clipboard. Open the folder you want to copy the

>pictures into, hold the Ctrl key down and press the letter V. All the files

>will be copied there. Or, after selecting the files, look at the menu on the

>left and select Copy to.

>

>

>

>Different ways to try to repair the Autoplay window for downloading from

>either a camera or card reader. Also the same procedure can be used for a CD

>drive.

>

>

>

>Go from steps I to V, although step V may not be needed.

>

>I. Connect your camera to your computer, power it on and make sure you have

>pictures on your memory card. Make sure your batteries are good or better

>yet, use your AC adapter if your camera came with one.

If you are trying

>with a card reader, just connect it with a memory card

inserted and with

>*pictures on the memory card.*

>

>*Click on My Computer and look under Device with Removable storage. Your*

>*camera will be listed there and a drive letter will be assigned to it*

>*(something like H, G, etc.) You will use this drive letter in a step below.*

>*If you do not see your camera listed there you will need to repair your USB*

>*connection or you are on a network and the network drive is Z and XP cannot*

>*assign a drive letter to your camera so you will need to take care of this*

>*first. The steps below will not work if XP cannot assign a drive letter for*

>*your camera.*

>

>*II. Click on Start, click on Run and type the following in the textbox:*

>*REGSVR32 SHIMGVW.DLL*

>*and press Enter*

>*Note that there is a space between ...32 and SHI...*

>*This will take a few seconds to run.*

>

>*III. Go to the following site:*

>*<http://www.bigblackglasses.com/staff/downloads/autofix.exe>*

e

>

>*and download the autofix.exe file in one of your folder.*

Once done, double

>*click on this file. A window will open. Follow the directions on the screen.*

>

>*Once done, turn off the camera and reboot.*

>

>*IV. Power the camera on, wait 10–15 seconds for XP to recognize it, you*

>*should hear some beeping sound and the window should now open giving you the*

>*option of downloading photos from the camera.*

>

>*V. You may have to set the options for this window.*

>*Click on My Computer, your camera should be listed there under Devices with*

>*Removable Storage. Right click on it and click on Properties. In the opening*

>*window, click on the Autoplay tab and under Select, scroll to Pictures to*

>*select it. Select the button Prompt me... Do the same*

thing for a CD drive.

>

>

>

>You can also download the autofix.exe file from the following site if the

>above site is not available. You can also let Microsoft scan and try to fix

>all from this site instead of downloading the file. If you use this

>procedure, run the REGS..... command above before going to this site.

>

>[http://www.microsoft.com/downloads/details.aspx?](http://www.microsoft.com/downloads/details.aspx?FamilyID=c680a7b6-e8fa-45c4-a171-1b389cfacdad&DisplayLang=en)

FamilyID=c680a7b6-e8fa-45c4-a171-

1b389cfacdad&DisplayLang=en

>

>

>

>

>

>"nlc" <anonymous@discussions.microsoft.com> wrote in message

>news:B4974043-6958-48A6-9FDE-

F698AC4E0FFE@microsoft.com...

>> I used to be able to transfer my photos from my smartmedia card to my

>computer using a card reader. Now, when I connect it to the USB and slide in

>the card, the camera and scanner wizard does not open. I have to use my

>cameras software, which is OK, but I prefer to use a card reader. I can go

>to My computer, and right click on the icon for the removable media and

>choose open, but then I have to drag each picture to the folder I want to

>put it in. This has happened before, and then the wizard would start to

>work. Now it doesn't open at all. Any suggestions would be appreciated!

>

>

>.

>